

TYPE. Antitank mine

COLOR. Camouflage-painted

CASE. Wooden box

WEIGHT. 141/4 pounds

**EXPLOSIVE.** 11 pounds of TNT

FM 5-31 1 NOV 1943 101,03-0

#### **FUNCTIONING**

When armed with friction fuze

- 1. Pressure of 100 to 360 pounds on cover crushes one or more fuzes.
- 2: Flash from friction compound in crushed fuze explodes de-
- 3. Detonator explodes mine.



ITALIAN PERCUSSION FUZE


When armed with percussion fuze

- 1. Load on cover forces fuze lid downward.
- 2. Fuze lid crushes bakelite supporting cones and forces strikers down.
- 3. Upturned cone at base of striker breaks apart bakelite striker sleeve, permitting striker to continue downward.
- 4. Striker fires percussion cap.
- 5. Flame from cap explodes detonator—main charge.

#### DISARMING

Avoid applying pressure on false pressure lid. If mine appears deteriorated, or has been disturbed by blast or artillery fire, destroy by hand-placed charges.

#### DEFUZING



1. Open clips and remove



2. Remove fuzes and detonators.



- 3. Detach detonators from percussion type fuzes. Detonators are not detachable from friction type.
- 4. Plug arming holes and prepare mine for transport.

#### INSTALLING AND ARMING

- 1. Remove cover.
- 2. Remove detonators and fuzes from storage recesses.
- 3. Fasten detonators to fuzes and insert into corner holes.
- 4. Replace cover and fasten clips.
- 5. Place mine in hole, with cover 2 to 3 inches below ground surface.
- 6. Cover with earth, and camouflage.

#### PACKING AND TRANSPORTING



Before transporting, each mine is packed as follows:

- 1. Insert wooden spacer cubes with pins in four fuze holes.
- 2. Place fuzes upside down in circular recesses in lid piece.
- 3. Store detonators in wooden block. Lug on block fits into another circular recess in lid piece.


#### **RE-USE**

Make sure dowel pins in cover are not partially sheared. Inspect fuzes for cracks.

#### NOTE

Mine was designed to avoid detection by mine detectors. However American detector detects mine at 6 inches.

# ITALIAN WOODEN-BOX MINE



TYPE. Antitank mine

CASE. Wooden box

**EXPLOSIVE.** 5½ pounds gelignite

#### FUNCTIONING

1. Pressure of 185 to 380 pounds on cover shears copper shear pins.

101.04-a

Springs drive strikers onto percussion caps.
Caps explode detonators—main charge.

FM 5-31 1 NOV 1943

# ITALIAN WOODEN-BOX MINE

#### DISARMING

Inspect for booby traps before moving.

#### DEFUZING

- 1. Remove cover.
- 2. Lift out fuzes.
- 3: Remove detonators.


### INSTALLING AND ARMING

- 1. Remove cover.
- 2. Insert detonators in holes in mine lid.
- 3. Place fuzes in detonators.
- 4. Replace cover and fasten with wire handles.
- 5. Bury and camouflage.

#### **RE-USE**

Make sure shear pins are not partially sheared.

### SPACE FOR NOTES



TYPE. Antipersonnel mine and booby trap

COLOR. Gray

CASE. Sheet metal surrounded by steel spiral

WEIGHT. 13/4 pounds

**EXPLOSIVE.** 3½-ounce borehole charge


**EFFECT.** Effective fragmentation within radius of 10 yards; dangerous at greater distances.

EMPLOYMENT. As antipersonnel mine in forward areas.

FM 5-31

1 NOV 1943

102.01-a



### FUNCTIONING

Trip-wire pin holds striker in cocked position.


- 1. Pull on trip-wire pin releases striker.
- 2. Striker driven by striker spring sets off cap—detonator—main charge.

102.01-ь

1 NOV 1943

FM 5-31

#### DISARMING




p wires all slide cap older to safety



2. Cut trip wires,

- Remove pin and lower striker gently. Notch in cap holder res end of striker when holder is in safe position.

## FUT NG



- T. Remove percussion cap from holder.
- 2. Unscrew striker group and remove detonator.

#### INSTALLING AND ARMING

- 1. Drive metal-covered picket in ground to form hole for mine. Remove.
- 2. Place mine upright in hole, with  $7\frac{1}{2}$  inches extending above ground.
- 3. Insert detonator and screw on striker group.
- 4. Lay trip wire and anchor other end.
- 5. Raise striker and insert pin in bottom hole,
- 6. Attach trip wire to pin.
- 7. Camouflage
- 8. Place cap in cap holder, and push to armed position.


### PACKING AND TRANSPORTING

Wooden box contains 20 mines, one mallet, and one metal covered wooden picket 15 inches long and 1½ inches in diameter.

#### NOTE

It is possible to arm this mine by inserting the safety pin in the top hole. Disarm by pulling up on striker and sliding cap holder to safe position.

#### SPACE FOR NOTES



TYPE. Antipersonnel mine


COLOR. Black

CASE. Sheet metal


WEIGHT. 21/4 pounds

EXPLOSIVE. 4-pound powdered TNT

FFECT Causes casualties within radius of 10 to 15 yards.



# ITALIAN B4 MINE



#### FUNCTIONING

- 1. When tension wire is released, or either of two trip cords is pulled, keyhole slot in trip key disengages striker.
- 2. Striker, driven by striker spring, sets off percussion capdetonator—booster—main charge.

102.02-b 1 NOV 1943 FM 5-31